

Table of Contents

How to add sudo rights in Quattor.....	1
--	---

How to add sudo rights in Quattor

System wide sudo rights are defined in `pro_system_lhcb_ux.tpl`. New system wide rights should be added there. Other rights should be added either in the host template if it concerns only one host, or in a `admin_*` template which will be included in hosts concerned.

Sudo rights are defined like this :

```
"/software/components/access_control/roles/ROLE_NAME" = list(UG_LIST);  
"/software/components/access_control/privileges/acl_sudo/role/ROLE_NAME/0/targets" = list("+span:  
"/software/components/access_control/privileges/acl_sudo/role/ROLE_NAME/0/commands" = list(CMD);
```

Where **ROLE_NAME** is a name defining the role (eg. : `muhv_admins`), **UG_LIST** is a coma separated list of users and/or groups, with groups enclosed in a `escape()` function (eg : `"loic", escape("%muon")`) and **CMD** a list of commands as defined in the sudoers man page (eg. : `"ALL=(ALL) NOPASSWD: /sbin/service hvcard *"`).

This topic: LHCb > SudoInQuattor

Topic revision: r3 - 2008-03-11 - LoicBrarda



Copyright &© 2008-2019 by the contributing authors. All material on this collaboration platform is the property of the contributing authors.

Ideas, requests, problems regarding TWiki? Send feedback